







Product Support v / Graphics

Article ID: 000096688 | Content Type: Error Messages | Last Reviewed: 09/27/2023

Update Check Failed After Updating the Intel® Graphics Driver Using the Intel® Arc™ Control

#### Summary

Description

Resolution

#### **Environment**

#### **Operating System**

Windows 11\* Family, Windows® 10 family

#### Description

When you have updated the graphics driver using the Intel® Arc™ Control and the software checks for an update it will scan endlessly for an update then it will trigger an error message "We timed out looking for updates Intel® Driver & Support Assistant may be offline or having trouble finding the latest drivers. We'll check again in a few minutes."



#### Resolution

1. **Download** Display Driver Uninstaller (DDU)

software

and extract the file.

- 2. Open DDU \*\*\*\*.exe and run the extract program.
- 3. **Reboot** into Windows\* safe mode. (**Refer** to Start your PC in safe mode in Windows

.)

- 4. **Go to** the DDU extract path and **double-click** the *Display Driver Uninstaller.exe* to open the DDU.
- 5. Click Close in the Options window.
- 6. **Select** device type to GPU and **select** device to INTEL.
- 7. **Click** *Clean and restart*, wait for the software to finish the process, and auto-reboot Windows into normal mode.
- 8. Install the latest driver available for your Intel® Graphics card

Related articles

How to Use the Display Driver Uninstaller (DDU) to Uninstall an Intel® Graphics Driver

Related Products

This article applies to 17 products

Show all 💙

## Need more help?

### Contact support

Disclaimer  All postings and use of the content of	on this site are subject to Intel.co	m Terms of Use.		
Company Overview				
Contact Intel				
Newsroom				
Investors				
Careers				
Corporate Responsibility				
Diversity & Inclusion				
Public Policy				
rubile rolley				
f	X	in	ı	D
© Intel Corporation				
© Intel Corporation Terms of Use				
·				
Terms of Use				
Terms of Use *Trademarks				
Terms of Use *Trademarks Cookies				
Terms of Use *Trademarks Cookies Privacy				
Terms of Use *Trademarks Cookies Privacy Supply Chain Transparency				
Terms of Use *Trademarks Cookies Privacy Supply Chain Transparency Site Map				
*Trademarks  Cookies  Privacy  Supply Chain Transparency  Site Map  Your Privacy Choices   Notice at Collection  Intel technologies may require enable secure. // Your costs and results may  Notices and Disclaimers	vary. // Performance varies by us	activation. // No product or component ie, configuration and other factors. // Se g human rights and avoiding complicity	e our complete legal	

recognized human right.

# intel,